




Settings

Square



The code only required to provide the expanded state of the icon, which is 48DP. It is written to size down from 48DP to 36 DP (being in selected state in the center, to deselect).

Icons



H1 Settings (small)



Roboto Condensed Light #757575
Font size 24 sp
One line 14 characters
Two lines 28 characters max

T1 Change watch face

Roboto Condensed Light #ffffff
Font size 12 SP
One line 15 characters
Three lines 45 characters max


Adjust brightness

Roboto Condensed Light #757575
Font size 12 SP
One line 15 characters
Three lines 45 characters max



Micro Apps

Square



Icons



40 DP



52 DP
(when highlighted, default)



Background color #ffffff

T1

Google (Selected title)

Roboto Condensed Light #757575

Font size 12 SP (center with logo)

One line 15 characters

Three lines 45 characters max

Agenda (unselected title)

Roboto Condensed Light #b3b3b3

Font size 12 SP

One line 15 characters

Three lines 45 characters max

Note:


Only 52 DP icons is needed. It will be compressed down to 40 DP by code when deselected.

Notifications

Square



Interactive mode with hotword while being charged




At small font settings



H1 Sam Blitzstein

Roboto Condensed Light #b3b3b3
Font size 14 sp
One line 22 characters max



H2 Sam Blitzstein



Roboto Condensed Light #b3b3b3
Font size 20 sp
One line 20 characters max

T1 About the trip to Mexico...


Roboto Condensed Light #000000
Font size 20 SP (center with logo)
One line 18 characters
Three lines 54 characters max

Action Buttons

Square



Action Icons



Center on device

Connected (Blue)

Circle 100 DP Color #0288d1

Disconnected (Grey)

Circle 100 DP Color #757575

Icon 64 DP Color #ffffff

H1 Open on phone




One line use 16 characters
max in 18 sp

Two lines use 36 characters
max in 14 sp

Center align text between top
and bottom of button of circle

Media Player

Square



The next button is being tapped



36 DP



30 DP

Artist Name


Roboto Condensed Light #b3b3b3
Font size 16 SP
One line 13 characters then ellipse

Song Title


Roboto Condensed Light #212121
Font size 16 SP
One line 13 characters then ellipse

Hotword and Status Icons


Square



Google Custom
Hotword + Indicator Position




Third Party
Hotword + Indicator Position




Settings


Circular



Some devices have a chin at the bottom of the screen.
Note that chin heights range from 20 to 23DP depending on the model.



Icons



H1 Settings



Roboto Condensed Light #757575
Font size 24 sp
One line 14 characters
Two lines 28 characters max

T1 Change watch face

Roboto Condensed Light #ffffff
Font size 12 SP
One line 15 characters
Three lines 45 characters max


Adjust brightness

Roboto Condensed Light #757575
Font size 12 SP
One line 15 characters
Three lines 45 characters max




Micro Apps

Circular



Some devices have a chin at the bottom of the screen.
Note that chin heights range from 20 to 23DP depending on the model.

Icons




T1 Google (Selected title)
Roboto Condensed Light #757575
Font size 12 SP (center with logo)
One line 15 characters
Three lines 45 characters max

Flashlight (unselected title)
Roboto Condensed Light #b3b3b3
Font size 12 SP
One line 15 characters
Three lines 45 characters max


Note:
Only 52 DP icons is needed. It will be compressed down to 40 DP by code when deselected.

Notifications

Circular



Some devices have a chin at the bottom of the screen.
Note that chin heights range from 20 to 23DP depending on the model.



Product Icons



H1 Sam Blitzstein



Roboto Condensed Light #b3b3b3
Font size 20 sp
One line 20 characters max

T1 About the trip to Mexico...

Roboto Condensed Light #000000
Font size 20 SP (center with logo)
One line 18 characters
Three lines 54 characters max


Action Buttons

Circular



Some devices have a chin at the bottom of the screen.
Note that chin heights range from 20 to 23DP depending on the model.

Action Icons



Center on device

Connected (Blue)

Circle 100 DP Color #0288d1

Disconnected (Grey)

Circle 100 DP Color #757575

Icon 64 DP Color #ffffff

H1 Open on phone


One line use 16 characters
max in 18 sp

Two lines use 36 characters
max in 14 sp


Center align text between top
and bottom of button of circle

Media Player

Circular



Some devices have a chin at the bottom of the screen.
Note that chin heights range from 20 to 23DP depending on the model.



Artist Name

Roboto Condensed Light #b3b3b3
Font size 16 SP
One line 13 characters then ellipse

Song Title

Roboto Condensed Light #212121
Font size 16 SP
One line 13 characters then ellipse

Status Icons and Hotword Location

Circular

🔊 16 DP "Ok Google" 24 DP

